

## Blu-Ray to Burn Help

With the “Blu-Ray to Burn” option you download a large ISO file from our site to your local computer. An ISO file, also called a disc image, is a single file that’s an exact copy of an entire Blu-Ray. When you burn a Blu-Ray Disc from an ISO file, the new disc has the same menus and viewing quality as an original disc delivered by mail.

Making a Blu-Ray from an ISO file is very easy to do on Windows and MAC computers. Please remember that a DVD burner is not the same as a Blu-Ray burner. You must have a Blu-Ray burner (not just Blu-Ray player) on your computer, a blank Blu-Ray Recordable Disc (BD-R) and the correct software.

Here are the most common steps.

### Windows 7

You can burn an ISO file to a recordable Blu-Ray by using Windows Disc Image Burner. No additional software needed.

1. Extract the ISO file from the ZIP you downloaded from TrueTeenBabes.tv and save on your desktop or another easy to remember location.
2. Insert a recordable Blu-Ray Disc into your disc burner.
3. Right-click the ISO file and then select Burn Disc Image from the pop-up menu.
4. If you have more than one disc burner installed select the burner that you want to use.
5. Click Burn to burn the disc.

**Notes:** Some parties have reported Windows 7 not completing ISO burns in a timely manner. Please review the section below for another option.

### Windows XP, Vista and Windows 7 with ImgBurn Software.

You can burn an ISO file to a recordable Blu-Ray by using Nero and other third-party software. Please review your software help files for tips on burning an image or ISO file.

We recommend the free software called “Imgburn”.

1. Visit Download.com and search for “Imgburn”, download it to your desktop and install it (uncheck any extra options such as toolbars).
2. Extract the ISO file from the ZIP you downloaded from TrueTeenBabes.tv and save on your desktop or another easy to remember location.
3. Insert your blank Blu-Ray disc into your Blu-Ray burner.
4. Open the Imgburn application and click “Write image file to disc”.
5. Click the magnifying glass file icon in the “Source” section to browse your computer and select your ISO file.

6. Click the large disc icon button at the bottom left of the window to automatically begin burning your Blu-Ray.

### **Mac OS X**

1. Extract the ISO file from the ZIP you downloaded from TrueTeenBabes.tv and save on your desktop or other easy to remember location.
2. Check if your computer has a Blu-Ray drive capable of burning Blu-Rays by clicking the Apple icon in the top left corner of the screen> “About This Mac”> “More Info...”> “Hardware”> “Device Manager”. It should list “Blu-Ray-Write” next to your Blu-Ray drive. MACs do not come standard with Blu-Ray drives or burners so if you have one it will likely be an external unit attached by Firewire, USB or eSata cable.
3. Open the software that came with your Blu-Ray Burner, most likely Roxio Toast, and follow the wizard or help files.

---

The Blu-Ray you have created mimics the video stored on an original, physical disc. It plays in your computer or Blu-Ray player exactly the same way as the Blu-Ray discs we send through the mail.

Please remember that by purchasing from TrueTeenBabes.tv you agreed that you will not distribute, or allow to be copied, any of the products purchased, in whole or part, without prior written consent from James S. Grady d/b/a Group Five Photosports, LLC and TrueTeenBabes™ and that infringement of that agreement and/or the copyrights of James S. Grady will result in legal action in the United States District Court for the District of Colorado.